


PipelineFX Metered License Portal Account Setup

Login to the Metered Licensing Portal at <https://metered.pipelinefx.com>

Create a user account

Follow the link at the bottom of the login pane to create a new account.


A screenshot of the PipelineFX Metered License Portal login form. The form is centered on a dark gray background. It features a light gray rounded rectangle containing a circular placeholder for a profile picture at the top. Below the placeholder are two input fields: 'Username' and 'Password', each with a small eye icon to its right. Under the password field is a checkbox labeled 'Remember me'. A blue 'Sign in' button is positioned below the checkbox. At the bottom of the form, there are two links: 'Forgot your password? [click here](#)' and 'New user? [create a new user account](#)'. The 'create a new user account' link is highlighted with a green rectangular border.

Make a note of the user name and password, you'll need them for the Metered License Agent (MLA) installation.

Once you've completed the user signup, you will receive an email with the subject line: **PipelineFX metered license server: New user account activation**. You must click on the link in that email to activate your user account.

Once your user account has been activated, you'll have the option to "Create a company account" or "Join an existing Company account".

During the initial setup, you'll want to **Create a new Billing account**.



PipelineFX
Qube Metered Licensing


Billing Account Name

Reporting Contact

Billing Contact

- **Account Name:** required - this should be your company or studio name, not your user name
- **Reporting Contact:** required - an email address to receive notifications, alerts, etc sent by the MLS
- **Billing Contact:** optional - an email address for you monthly invoice statements. If not defined, your invoice will be sent to the **Reporting Contact**.

Add your supervisor to the billing account



Add a Supervisor

MAC address

Description

Cancel

Save

Add a new supervisor

The **MAC Address** field is required, the **description** is optional.

The supervisor MAC address can be found several different ways:

- from the **hostid** field in your Qube License file:


```
#####
[license_S_6f3788f8477611e69118022eb6d22d19]
supervisor = 1
vendor = "PipelineFX L.L.C."
version = 6.9
type = unlimited
software = qube
hostid = 14:10:9F:E3:70:FD
assign_date = "Jul 11, 2016"
licensee = "PFX - jburk test"
exp_date = "Jul 11, 2017"
key = 106fac098b002188176b0fb45a0ab21f
#####
```

- from the output of the **qbping** command-line utility


```
supervisor - active - tag: 127.0.0.1 14:10:9F:E3:70:FD 6.9-0 rel-6.9-0001 osx - - host - 0/10
unlimited licenses (metered=0/0) - mode=0 (0).
```

- With **WranglerView**:


- Show the log panel with **View->Show/Hide Log Panel**



- run **Administration->Ping Supervisor**



- copy & the MAC address from the bottom of the log panel



Add a description to the new supervisor entry (optional)

Click in the **description** field to add or edit easily-recognizable name for your supervisor.

Supervisors and License Keys

| MAC Address ^ | Status ^ | Description (double-click value to edit) ^ | Version ^ | Current Type ^ |
|-------------------|------------|--|-----------|-------------------------------------|
| 11:22:33:22:33:11 | No records | [not set - double-click to edit] | | Manage License Keys |